

LZ210 - Bug #748

root root gst-root

12/23/2024 02:53 PM -

Status:	New	Start date:	12/23/2024
Priority:	High	Due date:	
Assignee:	Linx	% Done:	0%
Category:	S.W	Estimated time:	0.00 hour
Target version:		Spent time:	0.00 hour
OS:	LZ210	OS:	Ubuntu
CPU:	RK3562	Kernel:	6.1.8
Board:	LCH3576	APP:	-
Board/Device:	-	Progress:	100%
Build:	01	Build:	N/S
Board/Device:	01	Build:	YT8521SC
Image:	rk3562_lkd210_ubuntu22.04_12_13.img	EMMC:	-

Description

1 sudo -i root

2 gst-launch-1.0 v4l2src device=/dev/video22 ! video/x-raw,format=NV12,width=800,height=1280,framerate=30/1 ! fpsdisplaysink

3

4 neardi

5 sudo gst-launch-1.0 v4l2src device=/dev/video22 ! video/x-raw,format=NV12,width=800,height=1280,framerate=30/1 ! fpsdisplaysink

6

root neardi

History

- #1 - 12/27/2024 06:23 PM -
- File clipboard-202412271821-h3pum.png added
 - Subject changed from root gst-launch-1.0 to root gst-
 - Priority changed from Low to High

```

[ 4170.507822] rkCIF-mipi-lvds2: rkCIF_update_sensor_info: stream[3] get remote terminal sensor failed!
[ 4170.507835] rkCIF_scale_ch3: update_sensor_info failed -19
[ 4170.508756] rkCIF-mipi-lvds2: rkCIF_update_sensor_info: stream[0] get remote terminal sensor failed!
[ 4170.508788] rkCIF_tools_id0: update_sensor_info failed -19
[ 4170.509767] rkCIF-mipi-lvds2: rkCIF_update_sensor_info: stream[1] get remote terminal sensor failed!
[ 4170.509795] rkCIF_tools_id1: update_sensor_info failed -19
[ 4170.510767] rkCIF-mipi-lvds2: rkCIF_update_sensor_info: stream[2] get remote terminal sensor failed!
[ 4170.510810] rkCIF_tools_id2: update_sensor_info failed -19
[ 4179.875710] rkVdec2_reset:1390: cru reset
[ 4325.130869] rkVdec2_link_wait_result:1336: wait task break by signal
[ 4327.759162] rkVdec2_reset:1390: cru reset
[ 4353.121512] rkVdec2_link_wait_result:1336: wait task break by signal
[ 4355.747269] rkVdec2_reset:1390: cru reset
[ 4648.258545] rkVdec2_reset:1390: cru reset
[ 4937.607569] rkVdec2_reset:1390: cru reset
[ 4968.812664] rkVdec2_reset:1390: cru reset
[ 5256.657423] rkVdec2_reset:1390: cru reset
root@RK3562:~# gst-play-1.0 /home/neardi/ND_Test/sony1.mp4
Press 'k' to see a list of keyboard shortcuts.
Now playing /home/neardi/ND_Test/sony1.mp4
Redistribute latency...
MoTTY X11 proxy: Unsupported authorisation protocol
MoTTY X11 proxy: Unsupported authorisation protocol
arm_release_ver: gl3p0-01eac0, rk_so_ver: 10
WARNING Could not initialise Wayland output
WARNING debug information: ../ext/wayland/gstwaylandsink.c(526): gst_wayland_sink_find_display (): /GstWaylandSink:waylandsink0:
Failed to create GstWldDisplay: 'Failed to connect to the wayland display '(default)''
AL lib: (EE) ALCplaybackAlsa_open: Could not open playback device 'default': Device or resource busy
Redistribute latency...
Cannot connect to server socket err = No such file or directory
Cannot connect to server request channel
jack server is not running or cannot be started
JackShmReadWritePtr::~JackShmReadWritePtr - Init not done for -1, skipping unlock
JackShmReadWritePtr::~JackShmReadWritePtr - Init not done for -1, skipping unlock
AL lib: (EE) ALCplaybackAlsa_open: Could not open playback device 'default': Device or resource busy
WARNING Failed to connect: Connection refused
WARNING debug information: ../ext/pulse/pulsesink.c(616): gst_pulseringbuffer_open_device (): /GstPulseSink:audiosink-actual-sink-pulse
Redistribute latency...
Redistribute latency...
0:00:02.4 / 0:01:26.1

```

#2 - 01/10/2025 10:15 AM - Linux

ssh OK

Files

clipboard-202412271821-h3pum.png	165 KB	12/27/2024	
----------------------------------	--------	------------	--